


Simple hair rig

Learn the full workshop first. This card is a reminder, not a standalone tying lesson.

For a confirmed clean patch with a sinking bait. Not a pop-up rig or a solution to deep weed. The example uses a size-6 hook and 20lb coated braid; venue restrictions and your actual bait still take priority.



LAY OUT Size-6 Wide Gape X; 20lb N-Trap Soft; sinking bait; bait stop; stripping tool, scissors, needle and pullers. Add only the lead-end parts approved by your complete lead system.

- 1. Prepare** Cut about 30cm of 20lb N-Trap Soft. Strip roughly 10-13cm for the hair, whipping and short flexible section. Reject damaged fibres.
- 2. Bait first** Tie a small overhand hair loop. Mount the actual sinking bait and fit the stop. Set about 5-10mm of bait-to-bend clearance as a starting point.
- 3. Tie** Keep the hair behind the shank. Make about 7-9 neat knotless-knot turns, starting away from the eye join. Finish through the eye towards the point; moisten and seat.
- 4. Connect** For an approved quick-change connection, add the sleeve before a figure-of-eight loop. Around 15-20cm finished length is the clean-bottom starting example.
- 5. Check** Cover any quick-change crook. Where the complete kit requires a direct tie to its supplied swivel, use that connection instead. Test knots and the baited rig in water.

BEFORE EVERY CAST Check the permitted hook/barb and venue rules, sound line and connections, clear point and bait movement. With the hook removed or protected, test the complete system's prescribed line-break escape path. A water test or lead drop alone is not proof of safety.



Full illustrated workshop + component links


[Read the detailed simple hair rig guide](#)

Scan the QR or select a link. Print A4 at actual size; two pages per sheet makes A5 cards. Version: 2 October 2026.

Blowback rig

Learn the full workshop first. This card is a reminder, not a standalone tying lesson.

Use on a checked clean spot with a sinking bait. This rig uses a size-6 Wide Gape X, medium Kicker and a freely moving rig ring. It is not Korda's crimped Hybrid Stiff DF rig: never crimp N-Trap.



LAY OUT Size-6 Wide Gape X; 20lb N-Trap Soft; medium rig ring; standard medium Kicker; sinking bait and stop. Stripper, scissors, needle, pullers and compatible lead-end parts.

- 1. Prepare** Use 20lb N-Trap Soft with an intact stripped section. Tie the hair loop and mount the actual sinking bait. This knotted version is not a crimped Hybrid Stiff rig.
- 2. Ring** Secure the hair to the medium rig ring with an overhand knot. Locate it around the barb position (or equivalent on a barbless hook). Leave bait clearance.
- 3. Tie** Hold the hair behind the shank. Tie about 7-9 neat knotless-knot turns, with a point-side eye exit. Keep the moving ring outside the whipping.
- 4. Kicker** Seat the standard medium Kicker on the size-6 hook. It must fit without splitting or trapping the freely moving ring.
- 5. Finish** Use the compatible lead-end connection and about 15-20cm finished length for this clean-bottom example. Check knots, ring travel and the baited rig in water.

BEFORE EVERY CAST Check the permitted hook/barb and venue rules, sound line and connections, clear point and bait movement. With the hook removed or protected, test the complete system's prescribed line-break escape path. A water test or lead drop alone is not proof of safety.



Full illustrated workshop + component links


[Read the detailed blowback rig guide](#)

Scan the QR or select a link. Print A4 at actual size; two pages per sheet makes A5 cards. Version: 2 October 2026.

Ronnie / spinner rig

Learn the full workshop first. This card is a reminder, not a standalone tying lesson.

A low pop-up presentation for a checked spot where the boom can settle. It is not weed-proof. Use the specified sizes or follow a complete alternative manufacturer rig; the original 360-degree rig is not the same construction.



LAY OUT Matched hook / swivel / Kicker / bead sizes below; 25lb BASIX Boom; two Small 0.6mm Krimps and matching tool; pop-up, floss, putty and compatible lead-end connection.

- 1. Match** Size-4 Krank, large standard Kicker, size-11 spinner swivel, medium bait swivel and medium bead. BASIX Boom 25lb / 0.55mm pairs with Small 0.6mm Krimps.
- 2. Boom** Use the matching tool groove and maker's method for two crimped loops. About 15-20cm is the clean-bottom starting point. Retain visible tags and pull-check both joints.
- 3. Retain** Seat the hook eye on the spinner crook. Fully enclose the crook with the large Kicker. The hook must stay retained while the swivel remains free to turn.
- 4. Bait** Fit the medium bait swivel and gripping bead without crowding the point. Attach the pop-up with sound floss knots and check it cannot pull free.
- 5. Balance** Add putty near the boom-side swivel connection without blocking movement. Test and soak the actual bait: the boom stays down and the low pop-up section settles consistently.

BEFORE EVERY CAST Check the permitted hook/barb and venue rules, sound line and connections, clear point and bait movement. With the hook removed or protected, test the complete system's prescribed line-break escape path. A water test or lead drop alone is not proof of safety.



Full illustrated workshop + component links

[Read the detailed ronnie / spinner rig guide](#)

Scan the QR or select a link. Print A4 at actual size; two pages per sheet makes A5 cards. Version: 2 October 2026.

Solid PVA bag

Learn the full workshop first. This card is a reminder, not a standalone tying lesson.

For a checked spot where the bag can settle and dissolve freely. Not a way to make dense weed or snags safe. This version uses the complete Korda Inline Safety Kit: its lead, numbered insert with moulded-in ring swivel and tail rubber stay together.



LAY OUT Size-6 Wide Gape X; 18lb Super Natural braid; wafter and stop; complete 2.5oz Inline Safety Kit example; Solidz bag, dry compatible feed, PVA tape, scissors, needle and pullers.

- 1. Hooklink** Tie the knotless-knot hair rig in 18lb Super Natural uncoated braid. Aim for roughly 7-10cm finished length. Test the actual wafter so it does not lift the hook.
- 2. Inline kit** Match the lead and numbered insert. Use the kit's moulded-in ring swivel, tail rubber and prescribed routing, knot and release test. No added size-8 quick-change swivel.
- 3. Pack** Dry the rig and hands after testing. Add dry feed, baited hooklink, central lead and more feed. Keep the hook point clear of the line, lead and hard pellets.
- 4. Seal** Compact the contents and tie the neck with PVA tape without trapping the line. Trim carefully, tuck corners and dampen only where needed. Follow bag-maker venting advice.
- 5. Melt test** Sacrifice a matching bag in venue-temperature water. Check full release, residue and presentation; then make a fresh dry bag. Check the total lead + bait + bag casting load.

BEFORE EVERY CAST Check the permitted hook/barb and venue rules, sound line and connections, clear point and bait movement. With the hook removed or protected, test the complete system's prescribed line-break escape path. A water test or lead drop alone is not proof of safety.



Full illustrated workshop + component links

[Read the detailed solid pva bag guide](#)

Scan the QR or select a link. Print A4 at actual size; two pages per sheet makes A5 cards. Version: 2 October 2026.